# **3 Introduction**

#### **Parallel Computing**

A parallel computer is a collection of processors usually of the same type, interconnected to allow coordination and exchange of data.

The processors are primarily used to jointly solve a given problem.

#### **Distributed Systems**

A set of possibly many different types of processors are distributed over a larger geographic area.

Processors do not work on a single problem.

Some processors may act in a malicous way.

PA © Harald Räcke

12

# Cost measures

How do we evaluate parallel algorithms?

- time efficiency
- space utilization
- energy consumption
- programmability
- communication requirement
- ▶ ...

#### Problems

- performance (e.g. runtime) depends on problem size n and on number of processors p
- statements usually only hold for restricted types of parallel machine as parallel computers may have vastly different characteristics (in particular w.r.t. communication)

# Cost measures

#### How do we evaluate sequential algorithms?

- time efficiency
- space utilization
- energy consumption
- programmability
- ▶ ...

Asymptotic bounds (e.g., for running time) often give a good indication on the algorithms performance on a wide variety of machines.

PA © Harald Räcke 3 Introduction

13

# Speedup

Suppose a problem *P* has sequential complexity  $T^*(n)$ , i.e., there is no algorithm that solves *P* in time  $o(T^*(n))$ .

#### **Definition 1**

The speedup  $S_p(n)$  of a parallel algorithm A that requires time  $T_p(n)$  for solving P with p processors is defined as

$$S_p(n) = \frac{T^*(n)}{T_p(n)}$$

Clearly,  $S_p(n) \le p$ . Goal: obtain  $S_p(n) \approx p$ .

It is common to replace  $T^*(n)$  by the time bound of the best **known** sequential algorithm for P!

PA ©Harald Räcke

# Efficiency

#### **Definition 2**

The efficiency of a parallel algorithm A that requires time  $T_p(n)$ when using p processors on a problem of size n is

$$E_p(n) = \frac{T_1(n)}{pT_p(n)}$$

 $E_p(n) \approx 1$  indicates that the algorithm is running roughly p times faster with p processors than with one processor.

Note that  $E_p(n) \leq \frac{T_1(n)}{pT_{\infty}(n)}$ . Hence, the efficiency goes down rapidly if  $p \geq T_1(n)/T_{\infty}(n)$ .

# Disadvantage: cost-measure does not relate to the optimum sequential algorithm.

3 Introduction

וחר	1П	PA © Harald	
11101		© Harald	Räcke

# DAG model — computation graph

- nodes represent operations (single instructions or larger blocks)
- edges represent dependencies (precedence constraints)
- closely related to circuits; however there exist many different variants
- branching instructions cannot be modelled
- completely hardware independent
- scheduling is not defined

Often used for automatically parallelizing numerical computations.

# Parallel Models — Requirements

#### Simplicity

A model should allow to easily analyze various performance measures (speed, communication, memory utilization etc.).

Results should be as hardware-independent as possible.

#### Implementability


Parallel algorithms developed in a model should be easily implementable on a parallel machine.

Theoretical analysis should carry over and give meaningful performance estimates.

#### A real satisfactory model does not exist!

PA © Harald Räcke

PA © Harald Räcke 3 Introduction



Here, vertices without incoming edges correspond to input data. The graph can be viewed as a data flow graph.

PA © Harald Räcke

18

16

17

### DAG model — computation graph

The DAG itself is not a complete algorithm. A scheduling implements the algorithm on a parallel machine, by assigning a time-step  $t_v$  and a processor  $p_v$  to every node.

#### **Definition 3**

A scheduling of a DAG G = (V, E) on p processors is an assignment of pairs  $(t_v, p_v)$  to every internal node  $v \in V$ , s.t.,

- ▶  $p_v \in \{1, ..., p\}; t_v \in \{1, ..., T\}$
- $t_u = t_v \Rightarrow p_u \neq p_v$
- $(u, v) \in E \Rightarrow t_v \ge t_u + 1$

where a non-internal node x (an input node) has  $t_x = 0$ . *T* is the length of the schedule.

	3 Introduction		
UUU G Harald Räcke		20	

Note that the DAG model as defined is a non-uniform model of computation.

In principle, there could be a different DAG for every input size n.

An algorithm (e.g. for a RAM) must work for every input size and must be of finite description length.

Hence, specifying a different DAG for every n has more expressive power.

Also, this is not really a complete model, as the operations allowed in a DAG node are not clearly defined.

#### DAG model — computation graph

The parallel complexity of a DAG is defined as

 $T_p(n) = \min_{\text{schedule } S} \{T(S)\}$ .

 $T_1(n)$ : #internal nodes in DAG  $T_{\infty}(n)$ : diameter of DAG

Clearly,


 $T_p(n) \ge T_{\infty}(n)$  $T_p(n) \ge T_1(n)/p$ 

#### Lemma 4

A schedule with length  $\mathcal{O}(T_1(n)/p + T_{\infty}(n))$  can be found easily.

#### Lemma 5

Finding an optimal schedule is in general NP-complete.



All processors are synchronized.

In every round a processor can:

- read a register from global memory into local memory
- do a local computation à la RAM
- write a local register into global memory

22


# **PRAM Model**

Every processor executes the same program.

However, the program has access to two special variables:

- *p*: total number of processors
- $id \in \{1, \dots, p\}$ : the id of the current processor

The following (stupid) program copies the content of the global register x[1] to registers  $x[2] \dots x[p]$ .



PA ©Harald Räcke 3 Introduction

# **Different Types of PRAMs**

Simultaneous Access to Shared Memory:

- EREW PRAM: simultaneous access is not allowed
- CREW PRAM:

concurrent read accesses to the same location are allowed; write accesses have to be exclusive

- CRCW PRAM: concurrent read and write accesses allowed
  - commom CRCW PRAM all processors writing to x[i] must write same value
  - arbitrary CRCW PRAM values may be different; an arbitrary processor succeeds
  - priority CRCW PRAM values may be different; processor with smallest id succeeds

```
PA
©Harald Räcke
```

26

24

# **PRAM Model**

- processors can effectively execute different code because of branching according to *id*
- however, not arbitrarily; still uniform model of computation

Often it is easier to explicitly define which parts of a program are executed in parallel:

Algorithm 2 sum1: // computes sum of x[1]...x[p]2: // red part is executed only by processor 13:  $r \leftarrow 1$ 4: while  $2^r \le p$  do5: for  $id \mod 2^r = 1$  pardo6: // only executed by processors whose id matches7:  $x[id] = x[id] + x[id + 2^{r-1}]$ 8:  $r \leftarrow r + 1$ 9: return x[1]

Algorit	hm 3 sum	
1: // c	Somputes sum of $x[1] \dots x[p]$	
2: <i>r</i> ←	1	
3: <b>whi</b>	$e 2^r \le p do$	
4:	for $id \mod 2^r = 1$ pardo	
5:	$x[id] = x[id] + x[id + 2^{r-1}]$	
6:	$r \leftarrow r + 1$	
7: <b>retu</b>	<b>rn</b> <i>x</i> [1]	


The above is an EREW PRAM algorithm.

On a CREW PRAM we could replace Line 4 by for  $1 \le id \le p$  pardo

#### **PRAM Model** — remarks

- similar to a RAM we either need to restrict the size of values that can be stored in registers, or we need to have a non-uniform cost model for doing a register manipulation (cost for manipulating x[i] is proportional to the bit-length of the largest number that is ever being stored in x[i])
  - in this lecture: uniform cost model but we are not exploiting the model
- global shared memory is very unrealistic in practise as uniform access to all memory locations does not exist
- global synchronziation is very unrealistic; in real parallel machines a global synchronization is very costly
- model is good for understanding basic parallel mechanisms/techniques but not for algorithm development
- model is good for lower bounds

	3 Introduction	
UUU © Harald Räcke		28



# **Network of Workstations — NOWs**

- interconnection network represented by a graph G = (V, E)
- each  $v \in V$  represents a processor
- ► an edge {u, v} ∈ E represents a two-way communication link between processors u and v
- network is asynchronous
- all coordination/communiation has to be done by explicit message passing

ПП	PA © Harald Räcke
100	© Harald Räcke

3 Introduction

29

# **Network of Workstations — NOWs**

Computing the sum on a *d*-dimensional hypercube. Note that  $x[0] \dots x[2^d - 1]$  are stored at the individual nodes.

Processors are numbered consecutively starting from 0

#### Algorithm 4 sum 1: // computes sum of $x[0] \dots x[2^d - 1]$ 2: $\gamma \leftarrow 1$ 3: while $2^r \le 2^d$ do // $p = 2^d$ if *id* mod $2^r = 0$ then 4: *temp* $\leftarrow$ receive(*id* + 2<sup>*r*-1</sup>) 5: x[id] = x[id] + temp6: **if** *id* mod $2^{r} = 2^{r-1}$ **then** 7: $send(x[id], id - 2^{r-1})$ 8: $r \leftarrow r + 1$ ٩· 10: if id = 0 then return x[id]

# **Network of Workstations - NOWs**

#### Remarks

- One has to ensure that at any point in time there is at most one active communication along a link
- There also exist synchronized versions of the model, where in every round each link can be used once for communication
- In particular the asynchronous model is quite realistic
- Difficult to develop and analyze algorithms as a lot of low level communication has to be dealt with
- Results only hold for one specific topology and cannot be generalized easily

	3 Introduction	
UUU © Harald Räcke		32

# **Performance of PRAM algorithms**

Suppose we have a PRAM algorithm that takes time T(n) and work W(n), where work is the total number of operations.

We can nearly always obtain a PRAM algorithm that uses time at most

 $\lfloor W(n)/p \rfloor + T(n)$ 

parallel steps on p processors.

#### Idea:

- ▶  $W_i(n)$  denotes operations in parallel step i,  $1 \le i \le T(n)$
- simulate each step in  $[W_i(n)/p]$  parallel steps
- then we have

$$\sum_{i} \left[ W_{i}(n)/p \right] \leq \sum_{i} \left( \lfloor W_{i}(n)/p \rfloor + 1 \right) \leq \lfloor W(n)/p \rfloor + T(n)$$

# **Performance of PRAM algorithms**

Suppose that we can solve an instance of a problem with size n with P(n) processors and time T(n).

We call  $C(n) = T(n) \cdot P(n)$  the time-processor product or the cost of the algorithm.

The following statements are equivalent

- P(n) processors and time  $\mathcal{O}(T(n))$
- $\mathcal{O}(C(n))$  cost and time  $\mathcal{O}(T(n))$
- $\mathcal{O}(C(n)/p)$  time for any number  $p \le P(n)$  processors
- $\mathcal{O}(C(n)/p + T(n))$  for any number p of processors

PA ©Harald Räcke

3 Introduction

33

# Performance of PRAM algorithms Why nearly always? We need to assign processors to operations. every processor p<sub>i</sub> needs to know whether it should be active in case it is active it needs to know which operations to

perform

design algorithms for an arbitrary number of processors; keep total time and work low

# **Optimal PRAM algorithms**

Suppose the optimal sequential running time for a problem is  $T^*(n)$ .

We call a PRAM algorithm for the same problem work optimal if its work W(n) fulfills

$$W(n) = \Theta(T^*(n))$$

If such an algorithm has running time T(n) it has speedup

$$S_p(n) = \Omega\left(\frac{T^*(n)}{T^*(n)/p + T(n)}\right) = \Omega\left(\frac{pT^*(n)}{T^*(n) + pT(n)}\right) = \Omega(p)$$

3 Introduction

for  $p = \mathcal{O}(T^*(n)/T(n))$ .

PA ©Harald Räcke

# Example

Algorithm for computing the sum has work W(n) = O(n). optimal


 $T(n) = O(\log n)$ . Hence, we achieve an optimal speedup for  $p = O(n/\log n)$ .

One can show that any CREW PRAM requires  $\Omega(\log n)$  time to compute the sum.

This means by improving the time T(n), (while using same work) we improve the range of p, for which we obtain optimal speedup.

We call an algorithm worktime (WT) optimal if T(n) cannot be asymptotically improved by any work optimal algorithm.

PA © Harald Räcke 3 Introduction



Important criterion as communication is usually a major bottleneck.

38

36

37

# **Communication Cost**


Algorithm 5 MatrixMult(A, B, n)1: Input:  $n \times n$  matrix A and B;  $n = 2^k$ 2: Output: C = AB3: for  $1 \le i, j, \ell \le n$  pardo4:  $X[i, j, \ell] \leftarrow A[i, \ell] \cdot B[\ell, j]$ 5: for  $r \leftarrow 1$  to log n6: for  $1 \le i, j \le n; \ell \mod 2^r = 1$  pardo7:  $X[i, j, \ell] \leftarrow X[i, j, \ell] + X[i, j, \ell + 2^{r-1}]$ 8:  $C[i, j] \leftarrow X[i, j, \ell]$ 

On  $n^3$  processors this algorithm runs in time  $O(\log n)$ . It uses  $n^3$  multiplications and  $O(n^3)$  additions.

PA © Harald Räcke	3 Introduction

# **Alternative Algorithm**

Split matrix into blocks of size  $n^{2/3} \times n^{2/3}$ .



Note that  $C_{i,j} = \sum_{\ell} A_{i,\ell} B_{\ell,j}$ .

Now we have the same problem as before but  $n' = n^{1/3}$  and a single multiplication costs time  $\mathcal{O}((n^{2/3})^3) = \mathcal{O}(n^2)$ . An addition costs  $n^{4/3}$ .

work for multiplications:  $\mathcal{O}(n^2 \cdot (n')^3) = \mathcal{O}(n^3)$ work for additions:  $\mathcal{O}(n^{4/3} \cdot (n')^3) = \mathcal{O}(n^3)$ time:  $\mathcal{O}(n^2) + \log n' \cdot \mathcal{O}(n^{4/3}) = \mathcal{O}(n^2)$  What happens if we have n processors?

#### Phase 1

 $p_i$  computes  $X[i, j, \ell] = A[i, \ell] \cdot B[\ell, j]$  for all  $1 \le j, \ell \le n$  $n^2$  time;  $n^2$  communication for every processor

#### Phase 2 (round r)

 $p_i$  updates  $X[i, j, \ell]$  for all  $1 \le j \le n; 1 \le \ell \mod 2^r = 1$  $n \cdot n/2^r$  time; no communication

#### Phase 3

 $p_i$  writes *i*-th row into C[i, j]'s. *n* time; *n* communication

PA ©Harald Räcke

40

3 Introduction

# **Alternative Algorithm**

The communication cost is only  $\mathcal{O}(n^{4/3} \log n')$  as a processor in the original problem touches at most  $\log n$  entries of the matrix.

Each entry has size  $\mathcal{O}(n^{4/3})$ .

The algorithm exhibits less parallelism but still has optimum work/runtime for just n processors.

much, much better in practise